# TRANSFERRING EBOOKS TO A NOOK

1. Find a title. Click on Add to Bookbag to save the title for checkout. Be sure that you're checking out the right kind of file for your device! If you don't know what your device supports, you can checked the "Compatible Devices" section on WVDeli.



2. To reach the download screen, click Proceed to Checkout. Titles will stay in your Bookbag for at least 60 minutes (although some users have experienced longer times).

3. Select your lending period, then click Confirm Check Out.

## Check Out

### The Adventures of Sherlock Holmes

Lending period: [ 14 day checkout ▼ ]

| Adobe EPUB eBook | Use on: eBook-compatible computers & devices | Remove |

**My Account Notes:**
Maximum checkouts allowed at one time on my library card: **10**
Current number of titles checked out: **4**
Checkouts remaining after this checkout: **5**

[ Confirm Check Out ]

4. Click Download on the next screen.

## Download

**The Adventures of Sherlock Holmes**
Adobe EPUB eBook (289 kb)

[ Download ]

Click here to download the software
needed to use this Adobe EPUB eBook title.

Checked out on: Mar 20, 2012
Expires on: Apr 03, 2012

5. You will see this pop up. Make sure to click Open.



6. Digital Editions will automatically start. It might take a few seconds for the whole program to be visible. The book will probably open in READING VIEW (designing for reading on your computer screen).

7.  In order to transfer the book to your Nook, you'll need to click on the book icon in the top left corner. If you hover over it, you will get a popup that says GO TO LIBRARY VIEW.



8.  At this point, you'll probably want to connect your Nook if you haven't already.  Give the program a few minutes to recognize the device; you will see NOOK or MEDIA appear in the panel on the left side. **\*PLEASE NOTE INFO ABOUT ADOBE ID AUTHORIZATION ON THE LAST PAGE\***  If you have a Nook Color, please make sure that it's "awake"; Colors do not automatically activate when connected like older Nooks.

If you get this popup, just click X to close it.

9.  To transfer a book, we'll need to switch to LIBRARY VIEW, then click on the cover of the book that you'd like to send to your Nook.  Holding down the button on the mouse, drag it over to the word NOOK or MEDIA on the left side of the window.  When you see a + surrounded by green, you can let go of the mouse.



10.  Unplug the Nook from your computer and give it a second to reorganize your shelves and locate the new title.  Ordinarily, WVDELI titles will be stored in the My Documents section of the Nook.  You can navigate to that section by using the touchscreen on the Nook.

by Craig Lefteroff (2/9/2011)

## TOUCHSCREEN



Pressing < takes you to this screen…



For DELI stuff, you'll probably want to press MY LIBRARY.

by Craig Lefteroff (2/9/2011)

# POTENTIAL PROBLEMS

**\*ADOBE ID AUTHORIZATION —** Both your computer and your Nook should be authorized with an Adobe ID before you begin to transfer books.  You will probably be prompted by Adobe Digital Editions, but (if not), go to http://adobe.ly/9xXHgv and click Create an Adobe Account.  Use the same email and password when you connect your Nook and Adobe Digital Editions asks you to authorize the device.

If you get a message on your Nook that reads "User not activated"…

1.  Connect your Nook to your computer through a USB port.

2.  Go to My Computer on your desktop or press the Start button on your computer and click on Computer.  Then click on whatever drive represents your Nook.

3.  Click the Adobe Digital Editions folder to highlight it, then press Delete on your keyboard.  Click Yes to delete the folder.

| Name ▲ | Date modified | Ty |
|---|---|---|
| .adobe-digital-editions | 12/29/2010 7:52 PM | Fil |
| Digital Editions | 12/29/2010 2:40 PM | Fil |
| my audiobooks | 1/1/2000 12:02 AM | Fil |
| my B&N downloads | 1/1/2000 12:02 AM | Fil |
| my documents | 1/1/2000 12:02 AM | Fil |
| my music | 1/1/2000 12:02 AM | Fil |
| my screensavers | 1/1/2000 12:02 AM | Fil |
| my wallpapers | 1/1/2000 12:02 AM | Fil |
| Business Planning-Part01 | 12/30/2010 9:49 AM | VL |
| Business Planning-Part02 | 12/30/2010 9:50 AM | VL |

4.  Close the Adobe Digital Editions program (if it's open), then restart the Adobe Digital Editions program.

5.  If you're still getting an error, go to My Computer, then to your Nook.

6.  Delete the Digital Editions folder (it should be just underneath the Adobe Digital Editions folder).

7.  Close and restart the Adobe Digital Editions program.

8.  You'll probably have to go through the Authorize Device steps once more to authorize your Nook.


**INSTALLING OVERDRIVE MEDIA CONSOLE DIRECTLY ONTO THE NOOK**

It's possible to install the Mobile version of Overdrive Media Console directly onto most Nooks so that you don't have to connect to a desktop or laptop in order to download MP3 audiobooks.  You'll want to select the Android version of the Overdrive Media Console.   PLEASE NOTE THAT THIS DOES NOT APPEAR TO WORK CONSISTENTLY WITH NOOK COLOR!  If a patron is having issues with Nook Color, please ask them to download and transfer files from their desktop or laptop for now.  I'm looking for a solution to this problem, but they should have no problem transferring files from their computers.